

# msmtp

---

Version 1.8.0, 30 August 2018

Martin Lambers ([marlam@marlam.de](mailto:marlam@marlam.de))

---

This manual was last updated 30 August 2018 for version 1.8.0 of msmtmp.

Copyright (C) 2005, 2006, 2007, 2008, 2009, 2010, 2011, 2012, 2013, 2014, 2015, 2016, 2017, 2018 Martin Lambers

Copyright (C) 2011 Scott Shumate

Copying and distribution of this file, with or without modification, are permitted in any medium without royalty provided the copyright notice and this notice are preserved. These files are offered as-is, without any warranty.

# Table of Contents

<b>1</b>	<b>Introduction .....</b>	<b>1</b>
<b>2</b>	<b>Configuration files .....</b>	<b>2</b>
2.1	General commands .....	2
2.2	Authentication commands .....	3
2.3	TLS commands .....	4
2.4	Commands specific to sendmail mode .....	5
<b>3</b>	<b>Invocation .....</b>	<b>7</b>
3.1	Synopsis .....	7
3.2	Options .....	7
3.2.1	General options .....	7
3.2.2	Changing the mode of operation .....	7
3.2.3	Configuration options .....	8
3.2.4	Options specific to sendmail mode .....	9
3.3	Choosing an account .....	10
3.4	Exit code .....	11
3.5	Files .....	11
3.6	Environment .....	11
<b>4</b>	<b>Transport Layer Security .....</b>	<b>12</b>
<b>5</b>	<b>Authentication .....</b>	<b>14</b>
<b>6</b>	<b>Delivery Status Notifications .....</b>	<b>16</b>
<b>7</b>	<b>Sendmail mode .....</b>	<b>17</b>
7.1	Envelope-from address .....	17
7.2	Logging .....	17
7.3	Header handling .....	17
<b>8</b>	<b>Server information mode .....</b>	<b>18</b>
<b>9</b>	<b>Remote Message Queue Starting mode .....</b>	<b>19</b>

<b>10</b>	<b>Examples .....</b>	<b>20</b>
10.1	A user configuration file .....	20
10.2	A system wide configuration file .....	21
10.3	Using msmtplib with Mutt .....	22
10.4	Using msmtplib with mail .....	23
10.5	Using msmtplib with Tor .....	23
10.6	Aliases file .....	23
<b>11</b>	<b>Minimal SMTP server (msmtplib) .....</b>	<b>25</b>

# 1 Introduction

msmtp is an SMTP client.

In its default mode of operation, it reads a mail from standard input and sends it to a predefined SMTP server that takes care of proper delivery. Command line options and exit codes are compatible to sendmail.

The best way to start is probably to have a look at the Examples section. See Chapter 10 [Examples], page 20.

In addition to sendmail mode, there are two other modes of operation:

- Server information mode. In this mode, msmtp prints as much information as it can get about a given SMTP server (supported features, maximum mail size, . . .).
- Remote Message Queue Starting mode. In this mode, msmtp sends a Remote Message Queue Starting request for a host, domain, or queue to a given SMTP server.

Normally, a system wide configuration file and/or a user configuration file contain information about which SMTP server to use and how to use it, but all settings can also be configured on the command line.

The information about SMTP servers is organized in accounts. Each account describes one SMTP server: host name, authentication settings, TLS settings, and so on. Each configuration file can define multiple accounts.

Supported features include:

- TLS secured connections (including server certificate verification and the possibility to send a client certificate)
- Authentication methods PLAIN, LOGIN, CRAM-MD5 and EXTERNAL (and GSS-API, SCRAM-SHA-1, DIGEST-MD5, and NTLM when compiled with GNU SASL support)
- Internationalized Domain Names (IDN)
- DSN (Delivery Status Notification) support
- PIPELINING support for increased transmission speed
- RMQS (Remote Message Queue Starting) support (ETRN keyword)

## 2 Configuration files

msmtp supports a system wide configuration file and a user configuration file. Both are optional and need not exist.

If it exists and is readable, a system wide configuration file `SYSCONFDIR/msmtprc` will be loaded. Use `--version` to find out which `SYSCONFDIR` your version of msmtp uses.

The default user configuration file is `~/.msmtprc` or `$XDG_CONFIG_HOME/msmtp/config`. Accounts defined in the user configuration file override accounts from the system configuration file. Configuration file settings can be changed by command line options.

A configuration file is a simple text file. Empty lines and comment lines (first non-blank character is '#') are ignored. Every other line must contain a command and may contain an argument to that command. The argument may be enclosed in double quotes (").

If a file name starts with the tilde (~), this tilde will be replaced by `$HOME`.

If a command accepts the argument 'on', it also accepts an empty argument and treats that as if it was 'on'.

Commands are organized in accounts. Each account starts with the 'account' command and defines the settings for one SMTP account.

See Chapter 10 [Examples], page 20.

### 2.1 General commands

**'defaults'**

Set defaults. The following commands will set default values for all following account definitions in the current configuration file.

**'account name [: account[,...]]'**

Start a new account definition with the given name. The current default values are filled in (see [defaults], page 2).

If a colon and a list of previously defined accounts is given after the account name, the new account, with the filled in default values, will inherit all settings from the accounts in the list.

**'host hostname'**

The SMTP server to send the mail to. The argument may be a host name or a network address. Every account definition must contain this command.

**'port number'**

The port that the SMTP server listens on. The default is 25 ("smtp"), unless TLS without STARTTLS is used, in which case it is 465 ("smtps").

**'source\_ip [IP]'**

Set a source IP address to bind the outgoing connection to. Useful only in special cases on multi-home systems. An empty argument disables this.

**'proxy\_host [IP|hostname]'**

Use a SOCKS proxy. All network traffic will go through this proxy host, including DNS queries, except for a DNS query that might be necessary to resolve the proxy host name itself (this can be avoided by using an IP address as proxy).

host name). An empty argument disables proxy usage. The supported SOCKS protocol version is 5. If you plan to use this with Tor, see also Section 10.5 [Using msmtplib with Tor], page 23.

**‘proxy\_port [number]’**

Set the port number for the proxy host. An empty ‘number’ argument resets this to the default port, which is 1080 ("socks").

**‘timeout (off|seconds)’**

Set or unset a network timeout, in seconds. The argument ‘off’ means that no timeout will be set, which means that the operating system default will be used.

**‘protocol (smtp|lmtp)’**

Set the protocol to use. Currently only SMTP and LMTP are supported. SMTP is the default. See [port], page 2, for default ports.

**‘domain argument’**

This command sets the argument of the SMTP EHLO (or LMTP LHLO) command. The default is ‘localhost’, which is stupid but usually works. Try to change the default if mails get rejected due to anti-SPAM measures. Possible choices are the domain part of your mail address (provider.example for joe@provider.example) or the fully qualified domain name of your host (if available).

## 2.2 Authentication commands

See Chapter 5 [Authentication], page 14.

**‘auth [(on|off|method)]’**

Enable or disable authentication and optionally choose a method to use. The argument ‘on’ chooses a method automatically. Accepted methods are ‘plain’, ‘scram-sha-1’, ‘cram-md5’, ‘gssapi’, ‘external’, ‘digest-md5’, ‘login’, and ‘ntlm’. See Chapter 5 [Authentication], page 14.

**‘user [username]’**

Set the user name for authentication. An empty argument unsets the user name. Authentication must be activated with the ‘auth’ command.

**‘password [secret]’**

Set the password for authentication. An empty argument unsets the password. Consider using the ‘passwordeval’ command or a key ring instead of this command, to avoid storing plain text passwords in the configuration file. See Chapter 5 [Authentication], page 14.

**‘passwordeval [eval]’**

Set the password for authentication to the output (stdout) of the command eval. This can be used e.g. to decrypt password files on the fly or to query key rings, and thus to avoid storing plain text passwords. See Chapter 5 [Authentication], page 14.

`'ntlm domain [ntlm domain]'`

Set a domain for the `'ntlm'` authentication method. This is obsolete.

## 2.3 TLS commands

See Chapter 4 [Transport Layer Security], page 12.

`'tls [(on|off)]'`

Enable or disable TLS (also known as SSL) for secured connections. You also need `'tls_trust_file'` or `'tls_fingerprint'`, and for some servers you may need to disable `'tls_starttls'`.

`'tls_starttls [(on|off)]'`

Choose the TLS variant: start TLS from within the session (`'on'`, default), or tunnel the session through TLS (`'off'`).

`'tls_trust_file [file]'`

Activate server certificate verification using a list of trusted Certification Authorities (CAs). The file must be in PEM format. Some systems provide a system-wide default file, e.g. `/etc/ssl/certs/ca-certificates.crt` on Debian-based systems with the `'ca-certificates'` package. An empty argument disables this. You should also use `'tls_crl_file'`.

`'tls_crl_file [file]'`

Set a certificate revocation list (CRL) file for TLS, to check for revoked certificates. An empty argument disables this.

`'tls_fingerprint [fingerprint]'`

Set the fingerprint of a single certificate to accept for TLS. This certificate will be trusted regardless of its contents. The fingerprint should be of type SHA256, but can for backwards compatibility also be of type SHA1 or MD5 (please avoid this). The format should be `01:23:45:67:....`. Use `'--serverinfo --tls --tls-certcheck=off --tls-fingerprint='` to get the server certificate fingerprint.

`'tls_key_file [file]'`

Send a client certificate to the server (use this together with `'tls_cert_file'`). The file must contain the private key of a certificate in PEM format. An empty argument disables this feature.

`'tls_cert_file [file]'`

Send a client certificate to the server (use this together with `'tls_key_file'`). The file must contain a certificate in PEM format. An empty argument disables this feature.

`'tls_certcheck [(on|off)]'`

Enable or disable checks of the server certificate.

WARNING: When the checks are disabled, TLS sessions will be vulnerable to man-in-the-middle attacks!

`'tls_min_dh_prime_bits [bits]'`

Set or unset the minimum number of Diffie-Hellman (DH) prime bits accepted for TLS sessions. The default is set by the TLS library and can be selected by



using an empty argument to this command. Only lower the default (for example to 512 bits) if there is no other way to make TLS work with the remote server.

`'tls_priorities [priorities]'`

Set the priorities for TLS sessions. The default is set by the TLS library and can be selected by using an empty argument to this command. See the GnuTLS documentation of the `'gnutls_priority_init'` function for a description of the *priorities* string.

## 2.4 Commands specific to sendmail mode

See Chapter 7 [Sendmail mode], page 17.

`'from [address]'`

Set the envelope-from address. This is usually required, but sometimes `'auto_from'` is a useful alternative. See Section 7.1 [Envelope-from address], page 17.

`'auto_from [(on|off)]'`

Enable or disable automatic envelope-from addresses. The default is `'off'`. When enabled, an envelope-from address of the form `user@domain` will be generated. The local part will be set to `USER` or, if that fails, to `LOGNAME` or, if that fails, to the login name of the current user. The domain part can be set with the `'maildomain'` command; if that is empty, the address not have a domain part. See Section 7.1 [Envelope-from address], page 17.

`'maildomain [domain]'`

Set a domain part for the generation of an envelope-from address. See [auto\_from], page 5.

`'dsn_notify (off|condition)'`

Set the condition(s) under which the mail system should send DSN (Delivery Status Notification) messages. The argument `'off'` disables explicit DSN requests, which means the mail system decides when to send DSN messages. This is the default. The *condition* must be `'never'`, to never request notification, or a comma separated list (no spaces!) of one or more of the following: `'failure'`, to request notification on transmission failure, `'delay'`, to be notified of message delays, `'success'`, to be notified of successful transmission. The SMTP server must support the DSN extension. See Chapter 6 [Delivery Status Notifications], page 16.

`'dsn_return (off|amount)'`

This command controls how much of a mail should be returned in DSN (Delivery Status Notification) messages. The argument `'off'` disables explicit DSN requests, which means the mail system decides how much of a mail it returns in DSN messages. This is the default. The *amount* must be `'headers'`, to just return the message headers, or `'full'`, to return the full mail. The SMTP server must support the DSN extension. See Chapter 6 [Delivery Status Notifications], page 16.

`'add_missing_from_header [(on|off)]'`

This command controls whether to add a From header if the mail does not have one. The default is to add it. See Section 7.3 [Header handling], page 17.

`'add_missing_date_header [(on|off)]'`

This command controls whether to add a Date header if the mail does not have one. The default is to add it. See Section 7.3 [Header handling], page 17.

`'remove_bcc_headers [(on|off)]'`

This command controls whether to remove Bcc headers. The default is to remove them. See Section 7.3 [Header handling], page 17.

`'logfile [file]'`

Enable logging to the specified file. An empty argument disables logging. The file name `'-'` directs the log information to standard output. See Section 7.2 [Logging], page 17.

`'logfile_time_format [fmt]'`

Set or unset the log file time format. This will be used as the format string for the `strftime()` function. An empty argument chooses the default (`"%b %d %H:%M:%S"`). See Section 7.2 [Logging], page 17.

`'syslog [(on|off|facility)]'`

Enable or disable syslog logging. The *facility* can be one of `'LOG_USER'`, `'LOG_MAIL'`, `'LOG_LOCAL0'`, ..., `'LOG_LOCAL7'`. The default is `'LOG_USER'`. Syslog logging is disabled by default. See Section 7.2 [Logging], page 17.

`'aliases [file]'`

Replace local recipients with addresses in the aliases file. The aliases file is a plain text file containing mappings between a local address and a list of domain addresses. A local address is defined as one without an `'@'` character and a domain address is one with an `'@'` character. The mappings are of the form:

```
local: someone@example.com, person@domain.example
```

Multiple domain addresses are separated with commas. Comments start with `'#'` and continue to the end of the line.

The local address `'default'` has special significance and is matched if the local address is not found in the aliases file. If no `'default'` alias is found, then the local address is left as is.

An empty argument to the aliases command disables the replacement of local addresses. This is the default.

## 3 Invocation

### 3.1 Synopsis

- Sendmail mode (default):  
`msmtp [option...] [--] recipient...`  
`msmtp [option...] -t [--] [recipient...]`
- Server information mode:  
`msmtp [option...] --serverinfo`
- Remote Message Queue Starting mode:  
`msmtp [option...] --rmqs=(host|@domain|#queue)`

### 3.2 Options

Options override configuration file settings. They are compatible with sendmail where appropriate.

#### 3.2.1 General options

- `--version`  
Print version information, including information about the libraries used.
- `--help`    Print help.
- `-P`
- `--pretend`  
Print the configuration settings that would be used, but do not take further action. An asterisk (\*) will be printed instead of the password.
- `-v`
- `-d`
- `--debug`    Print lots of debugging information, including the whole conversation with the server. Be careful with this option: the (potentially dangerous) output will not be sanitized, and your password may get printed in an easily decodable format!

#### 3.2.2 Changing the mode of operation

- `-S`
- `--serverinfo`  
Print information about the SMTP server and exit. This includes information about supported features (mail size limit, authentication, TLS, DSN, ...) and about the TLS certificate (if TLS is active). See Chapter 8 [Server information mode], page 18.
- `--rmqs=(host|@domain|#queue)`  
Send a Remote Message Queue Starting request for the given host, domain, or queue to the SMTP server and exit. See Chapter 9 [Remote Message Queue Starting mode], page 19.

### 3.2.3 Configuration options

Most options in this category correspond to a configuration file command. Please refer to Chapter 2 [Configuration files], page 2, for detailed information.

`'-C filename'`

`'--file=filename'`

Use the given file instead of `~/.msmtp.rc` or `XDG_CONFIG_HOME/msmtp/config` as the user configuration file.

`'-a account'`

`'--account=account'`

Use the given account instead of the account named `'default'`. This option cannot be used together with the `--host` option. See [Choosing an account], page 10.

`'--host=hostname'`

Use this server with settings from the command line; do not use any configuration file data. This option cannot be used together with the `--account` option. It disables loading of configuration files. See [Choosing an account], page 10.

`'--port=number'`

Set the port number to connect to. See [port], page 2.

`'--source-ip=[IP]'`

Set or unset an IP address to bind the socket to. See [source-ip], page 2.

`'--proxy-host=[IP|hostname]'`

Set or unset a SOCKS proxy to use. See [proxy\_host], page 2.

`'--proxy-port=[number]'`

Set or unset a port number for the proxy host. See [proxy\_port], page 3.

`'--timeout=(off|seconds)'`

Set or unset a network timeout, in seconds. See [timeout], page 3.

`'--protocol=(smtp|lmtp)'`

Set the protocol. See [protocol], page 3.

`'--domain=[argument]'`

Set the argument of the SMTP EHLO (or LMTP LHLO) command. See [domain], page 3.

`'--auth[(on|off|method)]'`

Enable or disable authentication and optionally choose the method. See [auth], page 3.

`'--user=[username]'`

Set or unset the user name for authentication. See [user], page 3.

`'--passwordeval=[eval]'`

Evaluate password for authentication. See [passwordeval], page 3.

`'--tls[(on|off)]'`

Enable or disable TLS/SSL. See [tls], page 4.

- `--tls-starttls[=(on|off)]`  
Enable or disable STARTTLS for TLS. See [tls\_starttls], page 4.
- `--tls-trust-file=[file]`  
Set or unset a trust file for TLS. See [tls\_trust\_file], page 4.
- `--tls-crl-file=[file]`  
Set or unset a certificate revocation list (CRL) file for TLS. See [tls\_crl\_file], page 4.
- `--tls-fingerprint=[fingerprint]`  
Set or unset the fingerprint of a trusted TLS certificate. See [tls\_fingerprint], page 4.
- `--tls-key-file=[file]`  
Set or unset a key file for TLS. See [tls\_key\_file], page 4.
- `--tls-cert-file=[file]`  
Set or unset a cert file for TLS. See [tls\_cert\_file], page 4.
- `--tls-certcheck[=(on|off)]`  
Enable or disable server certificate checks for TLS. See [tls\_certcheck], page 4.
- `--tls-min-dh-prime-bits=[bits]`  
Set or unset minimum bit size of the Diffie-Hellman (DH) prime. See [tls\_min\_dh\_prime\_bits], page 4.
- `--tls-priorities=[priorities]`  
Set or unset TLS priorities. See [tls\_priorities], page 5.

### 3.2.4 Options specific to sendmail mode

- `-f address`
- `--from=address`  
Set the envelope-from address. See [from], page 5.  
If no account was chosen yet (with `--account` or `--host`), this option will choose the first account that has the given envelope-from address (set with the `'from'` command). If no such account is found, "default" is used. See [Choosing an account], page 10.
- `--auto-from[=(on|off)]`  
Enable or disable automatic envelope-from addresses. See [auto\_from], page 5.
- `--maildomain=[domain]`  
Set the domain part for the `--auto-from` address. See [maildomain], page 5.
- `-N (off|condition)`
- `--dsn-notify=(off|condition)`  
Set or unset DSN notification conditions. See [dsn\_notify], page 5.
- `-R (off|amount)`
- `--dsn-return=(off|amount)`  
Set or unset the DSN notification amount. See [dsn\_return], page 5. Note that `'hdrs'` is accepted as an alias for `'headers'` to be compatible with sendmail.

- `--add-missing-from-header[=(on|off)]`  
 Enable or disable the addition of a missing From header. See [add\_missing\_from\_header], page 5.
- `--add-missing-date-header[=(on|off)]`  
 Enable or disable the addition of a missing Date header. See [add\_missing\_date\_header], page 6.
- `--remove-bcc-headers[=(on|off)]`  
 Enable or disable the removal of Bcc headers. See [remove\_bcc\_headers], page 6.
- `-X [file]`  
`--logfile=[file]`  
 Set or unset the log file. See [logfile], page 6.
- `--logfile-time-format=[fmt]`  
 Set or unset the log file time format. See [logfile\_time\_format], page 6.
- `--syslog[=(on|off|facility)]`  
 Enable or disable syslog logging. See [syslog], page 6.
- `-t`  
`--read-recipients`  
 Send the mail to the recipients given in the To, Cc, and Bcc headers of the mail in addition to the recipients given on the command line.  
 If any Resent- headers are present, then the addresses from any Resent-To, Resent-Cc, and Resent-Bcc headers in the first block of Resent- headers are used instead.
- `--read-envelope-from`  
 Read the envelope from address from the From header of the mail. Currently this header must be on a single line for this option to work correctly.
- `--aliases=[file]`  
 Set or unset an aliases file. See [aliases], page 6.
- `-Fname` Msmtp adds a From header to mails that lack it, using the envelope from address. This option allows to set a full name to be used in that header.
- `--` This marks the end of options. All following arguments will be treated as recipient addresses, even if they start with a '-'.

The following options are accepted but ignored for sendmail compatibility: `-Btype`, `-bm`, `-G`, `-hN`, `-i`, `-L tag`, `-m`, `-n`, `-O option=value`, `-ox value`

### 3.3 Choosing an account

There are three ways to choose the account to use.

1. `--account=account`  
 Use the given account. Command line settings override configuration file settings.
2. `--host=hostname`  
 Use only the settings from the command line; do not use any configuration file data.

### 3. --from=*address* or --read-envelope-from

Choose the first account from the system or user configuration file that has a matching envelope-from address as specified by a [from], page 5, command. This works only when neither `--account` nor `--host` is used.

If none of the above options is used (or if no account has a matching [from], page 5, command), then the account "default" is used.

## 3.4 Exit code

The standard exit codes from `sysexits.h` are used.

## 3.5 Files

`'SYSCONFDIR/msmtpc'`

The system configuration file. Use the `--version` option to find out what SYSCONFDIR is on your platform.

`'~/.msmtpc or $XDG_CONFIG_HOME/msmtp/config.'`

The default user configuration file.

`'~/.netrc and SYSCONFDIR/netrc'`

The `netrc` file contains login information. Before prompting for a password, msmtp will search it in `~/.netrc` and `SYSCONFDIR/netrc`.

## 3.6 Environment

`'USER, LOGNAME'`

These variables override the user's login name when constructing an envelope-from address. `LOGNAME` is only used if `USER` is unset.

`'TMPDIR'`

Directory to create temporary files in. If this is unset, a system specific default directory is used. A temporary file is used to buffer the headers of the mail but not the mail body, so the file will not get very large.

`'EMAIL, SMTPSERVER'`

These environment variables are used only if neither `--host` nor `--account` is used and there is no default account defined in the configuration files. In this case, the host name is taken from `SMTPSERVER`, and the envelope from address is taken from `EMAIL`, unless overridden by `--from` or `--read-envelope-from`. Currently `SMTPSERVER` must contain a plain host name (no URL), and `EMAIL` must contain a plain address (no names or additional information).

## 4 Transport Layer Security

Transport Layer Security (TLS) "... provides communications privacy over the Internet. The protocol allows client/server applications to communicate in a way that is designed to prevent eavesdropping, tampering, or message forgery" (quote from RFC2246).

A server can use TLS in one of two modes:

- Via a STARTTLS command  
The session starts with the normal protocol initialization, and TLS is then started using the protocol's STARTTLS command.
- Immediately  
TLS is initialized before the normal protocol initialization. This requires a separate port.

The first mode is the default, but you can switch to the second mode by disabling `[tls_starttls]`, page 4.

When TLS is started, the server sends a certificate to identify itself. To verify the server identity, a client program is expected to check that the certificate is formally correct and that it was issued by a Certificate Authority (CA) that the user trusts. (There can also be certificate chains with intermediate CAs.)

The list of trusted CAs is specified using the `[tls_trust_file]`, page 4, command. Usually there is some system-wide default file available, e.g. `/etc/ssl/certs/ca-certificates.crt` on Debian-based systems, but you can also choose to select the trusted CAs yourself.

One practical problem with this approach is that the client program should also check if the server certificate has been revoked for some reason, using a Certificate Revocation List (CRL). A CRL file can be specified using the `[tls_crl_file]`, page 4, command, but getting the relevant CRL files and keeping them up to date is not straightforward. You are basically on your own.

A much more serious and fundamental problem is that you need to trust CAs. Like any other organization, a CA can be incompetent, malicious, subverted by bad people, or forced by government agencies to compromise end users without telling them. All of these things happened and continue to happen worldwide. The idea to have central organizations that have to be trusted for your communication to be secure is fundamentally broken.

Instead of putting trust in a CA, you can choose to trust only a single certificate for the server you want to connect to. For that purpose, specify the certificate fingerprint with `[tls_fingerprint]`, page 4. This makes sure that no man-in-the-middle can fake the identity of the server by presenting you a fraudulent certificate issued by some CA that happens to be in your trust list. However, you have to update the fingerprint whenever the server certificate changes, and you have to make sure that the change is legitimate each time, e.g. when the old certificate expired. This is inconvenient, but it's the price to pay.

Information about a server certificate can be obtained with `'--serverinfo --tls --tls-certcheck=off'`. This includes the issuer CA of the certificate (so you can trust that CA via `'tls_trust_file'`), and the fingerprint of the certificate (so you can trust that particular certificate via `'tls_fingerprint'`). See Chapter 8 [Server information mode], page 18.



TLS also allows the server to verify the identity of the client. For this purpose, the client has to present a certificate issued by a CA that the server trusts. To present that certificate, the client also needs the matching key file. You can set the certificate and key files using `[tls_cert_file]`, page 4, and `[tls_key_file]`, page 4. This mechanism can also be used to authenticate users, so that traditional user / password authentication is not necessary anymore. See the EXTERNAL mechanism in Chapter 5 [Authentication], page 14.

If you need to fine tune TLS parameters, have a look at the `[tls_priorities]`, page 5, and `[tls_min_dh_prime_bits]`, page 4, commands.

## 5 Authentication

Many SMTP servers require a client to authenticate before sending mail.

Usually a user name and a password are used for authentication. The user name specified in the configuration file with the [user], page 3, command. There are five different methods to specify the password:

1. Add the password to the system key ring.

Currently supported key rings are the Gnome key ring and the Mac OS X Keychain. For the Gnome key ring, use the command ‘secret-tool’ (part of Gnome’s libsecret) to store passwords:

```
$ secret-tool store --label=msmtp \
  host mail.freemail.example \
  service smtp \
  user joe.smith
```

On Mac OS X, use the Keychain Access GUI application. The ‘account name’ is same as the user name. The ‘keychain item name’ is smtp://<hostname> where <hostname> matches the ‘host’ argument.

2. Store the password in an encrypted files, and use [passwordeval], page 3, to specify a command to decrypt that file, e.g. using GnuPG. See Chapter 10 [Examples], page 20.
3. Store the password in the configuration file using the [password], page 3, command. (Usually it is not considered a good idea to store passwords in plain text files. If you do it anyway, you must make sure that the file can only be read by yourself.)
4. Store the password in ~/.netrc. This method is probably obsolete.
5. Type the password into the terminal when it is required.

It is recommended to use method 1 or 2.

Multiple authentication methods exist. Most servers support only some of them. Historically, sophisticated methods were developed to protect passwords from being sent unencrypted to the server, but nowadays everybody needs Chapter 4 [Transport Layer Security], page 12, anyway, so the simple methods suffice since the whole session is protected. A suitable authentication method is chosen automatically, and when TLS is disabled for some reason, only methods that avoid sending clear text passwords are considered.

The following user / password methods are supported:

- ‘PLAIN’  
A simple plain text method supported by almost all servers.
- ‘SCRAM-SHA-1’  
A method that avoids clear-text passwords.
- ‘CRAM-MD5’  
An obsolete method that avoids clear-text passwords, but is not considered secure anymore.
- ‘DIGEST-MD5’  
An overcomplicated obsolete method that avoids clear-text passwords, but is not considered secure anymore.

- ‘LOGIN’  
A non-standard clear-text method similar to (but worse than) PLAIN.
- ‘NTLM’  
An obscure non-standard method that is now considered broken. It sometimes requires a special domain parameter passed via [ntlm\_domain], page 3. Do not use it.

There are currently two authentication methods that are not based on user / password information and have to be chosen manually:

- ‘EXTERNAL’  
The authentication happens outside of the protocol, typically by sending a TLS client certificate (see Chapter 4 [Transport Layer Security], page 12).  
The EXTERNAL method merely confirms that this authentication succeeded; it does not perform the authentication. Thus it may not be necessary to use it for authentication to succeed, and if the server does not support the EXTERNAL method, this does not mean that it does not support authentication with TLS client certificates.
- ‘GSSAPI’  
With this method, the Kerberos framework takes care of secure authentication. Only a user name is required.

It depends on the underlying authentication library and its version whether a particular method is supported or not. Use `--version` to find out which methods are supported by your version.

## 6 Delivery Status Notifications

In situations such as delivery failure or delay, the mail system usually generates a message for the sender of the mail, informing him about the difficulties.

Delivery Status Notification (DSN) requests, defined in RFC 3461, try to give the sender of the mail control about how and when these DSN messages are sent. The SMTP server must support the DSN extension. See Chapter 8 [Server information mode], page 18.

A first parameter controls when such messages should be generated: never, on delivery failure, on delivery delay, and/or on success. This can be set with [dsn\_notify], page 5, and [-dsn\_notify], page 9.

A second parameter controls how much of the original mail should be contained in a DSN message: only the headers, or the full mail. This can be set with [dsn\_return], page 5, and [-dsn\_return], page 9. Note that this parameter only applies to DSNs that indicate delivery failure for at least one recipient. If a DSN contains no indications of delivery failure, only the headers of the message are returned.

## 7 Sendmail mode

### 7.1 Envelope-from address

The SMTP server expects a sender mail address for each mail. This is the envelope-from address. It is independent of the From header (because it is part of the mail *envelope*, not of the mail itself), but in most cases both addresses are the same.

Envelope-from addresses can be generated automatically (when [auto\_from], page 5, is enabled) or set explicitly with the [from], page 5, command.

### 7.2 Logging

When logging is enabled, msmtplib will generate one log line for each mail it tries to send.

The line will include the following information:

- Host name of the SMTP server: **host=hostname**
- Whether TLS was used: **tls=(on|off)**
- Whether authentication was used: **auth=(on|off)**
- The user name used for authentication (only if authentication is used): **user=name**
- The envelope-from address: **from=address**
- The recipient addresses: **recipients=addr1,addr2,...**
- The size of the mail as transferred to the server, in bytes (only if the delivery succeeded): **mailsize=number**
- The SMTP status code and SMTP error message (only in case of failure and only if available): **smtpstatus=number, smtpmsg='message'**. Multiline SMTP messages will be concatenated into one line.
- The msmtplib error message (only in case of failure and only if available): **errmsg='message'**
- The msmtplib exit code (from `sysexit.h`; 'EX\_OK' indicates success): **exitcode=EX\_...**

If a logfile is given with the [logfile], page 6, command, this log line will be prepended with the current date and time (formatted according to [logfile\_time\_format], page 6) and appended to the specified file.

If syslog logging is enabled with the [syslog], page 6, command, the log line is passed to the syslog service with the specified facility.

### 7.3 Header handling

Msmtplib transmits mails unaltered to the SMTP server, with the following exceptions:

- The Bcc header(s) will be removed. This behavior can be changed with the [remove\_bcc\_headers], page 6, command,
- A From header will be added if the mail does not have one. This can be changed with the [add\_missing\_from\_header], page 5, command. The header will use the envelope from address and optionally a full name set with the '-F' option.
- A Date header will be added if the mail does not have one. This can be changed with the [add\_missing\_date\_header], page 6, command.

## 8 Server information mode

In server information mode, `msmtp` prints as much information about the SMTP server as it can get and then exits.

The SMTP features that can be detected are:

- **SIZE**  
The maximum message size that the SMTP server accepts.
- **PIPELINING**  
Whether certain SMTP commands may be send in groups rather than one by one. This can speed up mail transmission if the recipient list is long. This feature is used automatically.
- **STARTTLS**  
See Chapter 4 [Transport Layer Security], page 12.
- **AUTH**  
See Chapter 5 [Authentication], page 14.
- **DSN**  
See Chapter 6 [Delivery Status Notifications], page 16.
- **ETRN**  
See Chapter 9 [Remote Message Queue Starting mode], page 19.

If TLS is activated for server information mode, the following information will be printed about the SMTP server's TLS certificate (if available):

- Owner information
  - Common Name
  - Organization
  - Organizational unit
  - Locality
  - State or Province
  - Country
- Issuer information
  - Common Name
  - Organization
  - Organizational unit
  - Locality
  - State or Province
  - Country
- General
  - Activation time
  - Expiration time
  - SHA256 fingerprint
  - SHA1 fingerprint (deprecated)

## 9 Remote Message Queue Starting mode

Remote Message Queue Starting (RMQS) is defined in RFC 1985. It is a way for a client to request that a server start the processing of its mail queues for messages that are waiting at the server for the client machine. If any messages are at the server for the client, then the server creates a new SMTP session and sends the messages at that time.

msmtp can only send the request (using the ETRN SMTP command); a mail server on the client side should then accept the connection of the remote SMTP server to receive the mail.

RMQS requests can be sent with the `[-rmqs]`, page 7, option. Destinations defined in RFC 1985 are:

- *host*  
Request the messages for the given host.
- *@domain*  
Request the messages for the given domain.
- *#queue*  
Request the delivery of the messages in the given queue.

## 10 Examples

### 10.1 A user configuration file

```
# Example for a user configuration file ~/.msmtprc
#
# This file focusses on TLS and authentication. Features not used here include
# logging, timeouts, SOCKS proxies, TLS parameters, Delivery Status Notification
# (DSN) settings, and more.

# Set default values for all following accounts.
defaults

# Use the mail submission port 587 instead of the SMTP port 25.
port 587

# Always use TLS.
tls on

# Set a list of trusted CAs for TLS. You can use a system-wide default file,
# as in this example, or download the root certificate of your CA and use that.
tls_trust_file /etc/ssl/certs/ca-certificates.crt

# Additionally, you should use the tls_crl_file command to check for revoked
# certificates, but unfortunately getting revocation lists and keeping them
# up to date is not straightforward.
#tls_crl_file ~/.tls-crls

# A freemail service
account freemail

# Host name of the SMTP server
host smtp.freemail.example

# As an alternative to tls_trust_file/tls_crl_file, you can use tls_fingerprint
# to pin a single certificate. You have to update the fingerprint when the
# server certificate changes, but an attacker cannot trick you into accepting
# a fraudulent certificate. Get the fingerprint with
# $ msmtprc --serverinfo --tls --tls-certcheck=off --host=smtp.freemail.example
tls_fingerprint 00:11:22:33:44:55:66:77:88:99:AA:BB:CC:DD:EE:FF:00:11:22:33

# Envelope-from address
from joe_smith@freemail.example
```



```

# Authentication. The password is given using one of five methods, see below.
auth on
user joe.smith

# Password method 1: Add the password to the system keyring, and let msmtplib get
# it automatically. To set the keyring password using Gnome's libsecret:
# $ secret-tool store --label=msmtplib \
#   host smtp.freemail.example \
#   service smtp \
#   user joe.smith

# Password method 2: Store the password in an encrypted file, and tell msmtplib
# which command to use to decrypt it. This is usually used with GnuPG, as in
# this example. Usually gpg-agent will ask once for the decryption password.
passwordeval gpg2 --no-tty -q -d ~/.msmtplib-password.gpg

# Password method 3: Store the password directly in this file. Usually it is not
# a good idea to store passwords in plain text files. If you do it anyway, at
# least make sure that this file can only be read by yourself.
#password secret123

# Password method 4: Store the password in ~/.netrc. This method is probably not
# relevant anymore.

# Password method 5: Do not specify a password. Msmtplib will then prompt you for
# it. This means you need to be able to type into a terminal when msmtplib runs.

# A second mail address at the same freemail service
account freemail2 : freemail
from joey@freemail.example

# The SMTP server of your ISP
account isp
host mail.isp.example
from smithjoe@isp.example
auth on
user 12345

# Set a default account
account default : freemail

```

## 10.2 A system wide configuration file

```

# A system wide configuration file is optional.

```

```
# If it exists, it usually defines a default account.
# This allows msmtp to be used like /usr/sbin/sendmail.
account default

# The SMTP smarthost
host mailhub.oursite.example

# Use TLS on port 465
port 465
tls on
tls_starttls off
tls_trust_file /etc/ssl/certs/ca-certificates.crt

# Construct envelope-from addresses of the form "user@oursite.example"
#auto_from on
#maildomain oursite.example

# Syslog logging with facility LOG_MAIL instead of the default LOG_USER
syslog LOG_MAIL
```

### 10.3 Using msmtp with Mutt

Create a configuration file for msmtp and add the following lines to your Mutt configuration file:

```
set sendmail="/path/to/msmtp"
set use_from=yes
set realname="Your Name"
set from=you@example.com
set envelope_from=yes
```

The ‘envelope\_from=yes’ option lets Mutt use the `-f` option of msmtp. Therefore msmtp chooses the first account that matches the from address `you@example.com`. Alternatively, you can use the `-a` option:

```
set sendmail="/path/to/msmtp -a my_account"
```

Or set everything from the command line:

```
set sendmail="/path/to/msmtp --host=mailhub -f me@example.com --tls"
```

See [Choosing an account], page 10.

If you have multiple mail accounts in your msmtp configuration file and let Mutt use the `-f` option to choose one, you can easily switch accounts in Mutt with the following Mutt configuration lines:

```
macro generic "<esc>1" ":set from=you@example.com"
macro generic "<esc>2" ":set from=you@your-employer.example"
macro generic "<esc>3" ":set from=you@some-other-provider.example"
```

Now you can use `<esc>1`, `<esc>2`, and `<esc>3` to switch accounts.

The following example uses a different approach: it maps the single key `<tab>` in Compose context for switching between the various account in a handy visual way. In the same

Compose context, = is mapped in order to show the current msmtplib account. This example was contributed by Thomas Baruchel.

```
# Define <tab> and = in order to switch or see the current msmtplib account
# Don't forget to put the right path for msmtplib binary
macro compose \Cx_ ":set sendmail"
macro compose \Cx| "\Cx_ = \"/usr/local/bin/msmtplib"
macro compose \Cx& ":macro compose \\t \\\Cx"
macro compose <tab> "\Cx0"
macro compose = "\Cx_\n"
# Put the account in the following lines (here three accounts)
# Don't forget to put the number of the account at the beginning
# of the line, and the number of the next account after the '&'
macro compose \Cx0 "\Cx|\n\n\Cx&1\n\Cx_\n" # default and switch to 1
macro compose \Cx1 "\Cx| -a example_account\n\n\Cx&2\n\Cx_\n" # switch to 2
macro compose \Cx2 "\Cx| -a gmail\n\n\Cx&0\n\Cx_\n" # switch to 0
# End of the accounts
```

## 10.4 Using msmtplib with mail

Define a default account, and put the following into ~/.mailrc:

```
set sendmail="/path/to/msmtplib"
```

You need to define a default account, because mail does not allow extra options to the msmtplib command line.

## 10.5 Using msmtplib with Tor

Use the following settings:

```
proxy_host 127.0.0.1
proxy_port 9050
tls on
```

Use an IP address as proxy host name, so that msmtplib does not leak a DNS query when resolving it.

TLS is required to prevent exit hosts from reading your SMTP session. You also need [tls\_trust\_file], page 4, or [tls\_fingerprint], page 4, to check the server identity. Do not set 'domain' to something that you do not want to reveal (do not set it at all if possible).

## 10.6 Aliases file

```
# Example aliases file

# Send root to Joe and Jane
root: joe_smith@example.com, jane_chang@example.com

# Send cron to Mark
cron: mark_jones@example.com

# Send everything else to admin
```

```
default: admin@domain.example
```

## 11 Minimal SMTP server (msmtpd)

Msmtpd is a minimal SMTP server that pipes mails to msmtp (or some other program) for delivery. It is intended to be used with system services that expect an SMTP server on the local host and cannot be configured to use the sendmail interface that msmtp provides.

Msmtpd handles local SMTP clients. It listens on 127.0.0.1 port 25 by default, but can also run without its own network sockets in inetd mode, where it handles a single SMTP session on standard input / output.

In the string that defines the command that msmtpd pipes each mail to, the first occurrence of ‘%F’ will be replaced with the envelope from address. Furthermore, all recipients of the mail will be appended as arguments. The command must not write to standard output, as that would mess up the SMTP session.

Only run msmtpd if you know you need it. Only use a local interface to listen on. Take care to run it with correct user rights and permissions (e.g. use ‘CAP\_NET\_BIND\_SERVICE’ to bind to port 25 instead of running as root, or use systemd with inetd service capabilities). Be aware that the pipe command will be run as the same user that msmtpd runs as.

Msmtpd handles the following options:

```

'--version'
    Print version information

'--help'    Print help.

'--inetd'   Start single SMTP session on stdin/stdout

'--interface=ip'
    Listen on the given IPv6 or IPv4 address instead of 127.0.0.1

'--port=number'
    Listen on the given port number instead of 25

'--command=cmd'
    Pipe mails to cmd instead of msmtp

```

Example for managing msmtpd with ‘start-stop-daemon’:

```

# start msmtpd
start-stop-daemon --start --pidfile /var/run/msmtpd.pid --make-pidfile --chuid msmtpd
# stop msmtpd
start-stop-daemon --stop --pidfile /var/run/msmtpd.pid --remove-pidfile --quiet --sig

```